

RC_BVM New User Guide

Introduction

RC_BVM is a version of the RC Standard server with an enhanced scripting engine. RC_BVM utilizes a commercial scripting engine, Brisk Virtual Machine 2, whose language is strongly influenced by the Blitz Basic family of languages.

RC_BVM brings many enhancements to the Realm Crafter scripting language. Among these changes are the additions of *Include* files, traditional Basic style control loops, custom user defined *types*, *arrays* and the ability to create and *Use* functions from precompiled *modules*, among other exciting changes.

There are also some features of the current RC scripting language that will no longer be valid. This list is much shorter than the list of additions. The functions GoTo(), GoToIf() and .Label are not supported in the RC_BVM Server.

Most of the commands which users of the standard RC scripting language are familiar with can be found in RC_BVM with little or no changes. Many commands have been tweaked to use more default values. This results in fewer script failures for failing to supply arguments which often seem more intuitive with default values. More on these changes later.

Sample Scripting

RC_BVM scripts will use a new file extension, .rsl to keep the scripts for RC_BVM and RC Standard more easily separated. Let's look at a simple RC_BVM script:

```
; RC_BVM utilizes a different character for commenting than does
; RC Standard. The semicolon (;) is now used for commenting
Function Main()

    ; Just as in RC Standard all script logic should begin within the Main function.
    Player = Actor() ; Note the identical syntax to RC standard

    ; Note that you can now use numbers and many symbols within variable names
    Player2 = ContextActor()

    ; String concatenation is now performed using the addition operator
    ; and no longer uses the $+ operator.
    Output(Player, "Hello " + Name(Player) + "!")

End Function
```

You will notice that there is very little about this script which is different than you would write for a RC Standard script. In general, if you can write a RC Standard script, you can write a simple RC_BVM script. If you are more familiar with any of the Blitz Basic family of languages, you will be even more at home with the RC_BVM style of scripting.

Variable Types

In Realm Crafter Standard, we are accustomed to a fully typeless system of variables. Variables can be any type at any time, all handled just about transparently. By type, we mean that variables are one of several types of values. Primarily, these will fall into *Int*, *Float* or *String* types. A *Int* or integer is a whole number either positive or negative. The maximum range of an integer in RC_BVM is -2147483648 to +2147483647. Floats or floating point numbers are numbers with fractional values, usually expressed in a decimal format. Strings are basically text values, or a collection of characters.

RC_BVM is not a typeless language. This means that variables are assigned a type at creation. While it is generally not necessary to explicitly declare the type, since RC_BVM will attempt to make that determination when the variable is first assigned a value, it is good practice to do so and may help to avoid hours of bug searches because the value you think is a *float* turns out to be a *int* because it wasn't properly initiated.

RC_BVM supports the same type shortcuts that Blitz basic uses, namely % for *int*, # for *float* and \$ for *string*. Declaring the variable at creation is generally done as in the following example:

```
; Integer Declaration
X% = 10
; Float Declaration
Y# = 5.5
; String Declaration
Z$ = "One"
```

Many operators can apply to more than one variable type, in this situation RC_BVM has a few simple rules to determine what the resulting type will be. This only applies to the three basic types and does not apply to user defined types.

If at least one of the supplied arguments is a *string*, then the result of the operation is a *string*.

If at least one of the supplied arguments is a *float*, then the result of the operation is a *float*

If none of the arguments is a *float* or a *string*, then the result is a *int*.

Arrays

Arrays are simply a list of values. **Arrays are created outside of functions using the Dim command.** Arrays can be created from any data type, but can only hold that data type. You cannot create a *int* array and put a string value into one of the positions.

Example:

```
Dim myList%(10)
Function Main()

    myList(1) = 10
    myList(2) = 9
    myList(5) = 5
    Output(Actor(), myList(2))

End Function
```

The above is an example of a single dimensional array, as it's simply a single list. RC_BVM supports multidimensional arrays as well by simply declaring it like so: `Dim myList%(10,10,10)` giving you ten arrays of ten arrays of ten values. For most RC scripting purposes a single dimensional array will be sufficient, however if a situation does arise, there is full support for multidimensional arrays.

Remember, if your arrays don't seem to be working properly, there are a couple of things which you should check. First, was the array declared outside of any functions? Next, is the declared type consistent with the type of data being placed into it?

Operators

Now we will cover some of the difference in operator behavior between RC Standard scripting and RC_BVM scripting. Mathematical operators remain nearly unchanged. The differences you will be more likely to notice are the string concatenation, or string addition operator (\$+ in RC Standard) has been replaced with the simple addition operator (+). Likewise the string comparison operator (\$=, in RC Standard) is now simply the same equals operator (=) that you would use in any mathematical operation.

While on the equality operator, lets cover another small change. No longer will you need to use \$= or == to compare values. RC_BVM is able to determine from the context of its usage if the = operator is comparing or assigning values, and able to determine if those values are numerical or string values.

Example:

```
X% = 10
Y% = 5
Z$ = "Hello"
W$ = " World!"

; Compare AND assign using the = operator
If X = Y
    Y = X
EndIf

; Compare And assign strings using the = operator
If Z$ = W$
    ; Do Nothing
Else
    Z$ = Z$ + W$
EndIf
```

Also changed is the bitwise And and the bitwise Or operators. In RC Standard these are & for And and | for Or. In RC_BVM simply use AND and OR.

And the last change to operators is the ! or Not operator. In RC Standard, this was used to make the determination that the results of a comparison were NOT true. Now we simply use <> (Less than and Greater than combined) instead.

Example:

```
; RC Standard version
If X != Y
    X = Y
EndIf

; RC_BVM version
If X <> Y
    X = Y
EndIf
```

Control Structures and Loops

Now, let's briefly cover the standard control structures available in RC_BVM.

We'll begin with the If..EndIf statements. While there is very little difference here from RC Standard there are a few small changes. To begin with, RC_BVM supports the Then statement.

Example:

```
If X > 10 Then
    Y = 1
Else
    Y = 0
EndIf
```

Notice that If no longer requires that the argument being tested be within parenthesis. It is certainly still acceptable, but no longer required. Also note that the Then keyword is now fully supported in RC_BVM.

Next we'll look at the For...Next statement. This type of loop is used to iterate through a set of instructions a given number of times. For example counting from one to ten.

Example:

```
For X = 1 To 10
    ; This will output the numbers 1 to 10 to the player
    Output(Actor(), X)
Next
```

Now we come to While...Wend which allows you to continue to loop through a set of instructions until a given condition is met.

Example

```
While X < 10
    ; This will output the numbers 0 thru 9 to the player
    Output(Actor(), X)
    X = X + 1
Wend
```

For another method of looping we can use the Repeat...Until loop. This, like the While loop allows us to operate on a set of instructions until a certain condition is met.

Example:

```
Repeat
    ; This will output the numbers 0 thru 9 to the player
    Output(Actor(), X)
    X = X + 1
Until X = 10
```

It is possible to repeat a loop indefinitely, simply use Repeat...Forever. Instead of placing a condition using Until, as in the above example, replace it with Forever for a perpetually looping section of script. While possible, perpetually looping scripts are not recommended, as this will impact server performance.

This covers the new looping controls in RC_BVM, next we will look at the Select...Case statement. The Select statement allows us to collect a value, and perform various actions depending on the current value of the Select statement. A *Default* value can be set that is run if any of the *Case* values aren't present.

Example:

```
X = 3
Select X
  Case 1
    Output (Actor (), "One")
  Case 2
    Output (Actor (), "Two")
  Case 3
    Output (Actor (), "Three")
  Default
    Output (Actor (), "Number not found")
End Select
```

This covers the new forms of control functions found in RC_BVM.

User defined Types

User defined types are essentially a collection of different variables under a single structure. Each *type* (or class) contains *fields*(or members) which hold values unique to each instance of the type.

Example:

```
Type TPlayer
    Field Name$
    Field Level%
End Type
```

This creates a new *type* named TPlayer which holds several values of differing variable types. The above is simply the structure of the new user *type* and must be declared outside of any functions. This deserves repeating, all types must be declared at the top of the script, before the Main function.

There can be many instances of each type, each with unique values in each of the fields. New *type* instances are created using the *new* keyword.

Example:

```
Type TPlayer
    Field Name$
    Field Level%
End Type

Function Main()
    thisPlayer.TPlayer = New TPlayer
End Function
```

Accessing the fields of the types is done using the member access operator or \ like so:

```
Type TPlayer
    Field Name$
    Field Level%
End Type

Function Main()
    thisPlayer.TPlayer = New TPlayer
    thisPlayer\Name = "Bill"
    thisPlayer\Level = 39
End Function
```

It is possible to create many instances of the *type*, each with its own set of *field* values that can each be accessed and manipulated independently. Here is an example of creating multiple instances of a single type. Next we will iterate through each of the instances and assign a value to the Level field.

Example:

```
Function Main()
    For I = 1 To 10
        thisPlayer.TPlayer = New TPlayer
        thisPlayer\Name = "Player " + I
    Next

    For thisPlayer.TPlayer = Each TPlayer
        thisPlayer\Level = Rand(1, 10)
    Next
End Function
```

As you can see types can be a great way to hold together groups of related data for easy access. Another feature of types in RC_BVM is the ability to use methods. A *method* is essentially a function within the type that is accessed in the same way you would access a *field* of the *type*.

```
Type TPlayer
  Field Name$
  Field Class$
  Field Level%

  ; Adds a last name to the Name field
  Method SetLastName (N$)
    Name = Name + " " + N$
  End Method
End Type

Function Main()
  thisPlayer.TPlayer = New TPlayer
  thisPlayer\Name = "Bill the Mighty"
  thisPlayer\Class = "Scholar"
  thisPlayer\Level = 39
  thisPlayer\SetLastName("the Mighty")
End Function
```

Methods can be a very powerful tool in RC_BVM. We are just scratching the surface of *types* and *methods* in this manual, as this can be a tricky subject for beginning programmers to get their heads around. The Brisk VM2 Scripting Language manual goes into more detail on types and methods and can be found [manual location]

Server And Scripting Enhancements

In the course of creating the BVM version of the RC Standard server, a few small changes to the server were made, some for security purposes some for stability purposes. Many of these changes have since been made a part of the RC Standard server. Some, however, are specific to the RC_BVM server. Among these changes are many new default values to the core RC scripting command set. Most of these will not be noticed by most of the users, but will make some commands behave a little more intuitively.

The biggest change to the existing command set is that `DialogInput()` no longer accepts multiple arguments. Instead all arguments should be in a single comma delimited string. The reason for this change is so that we can more easily include commas within the option strings. We do this by adding an optional delimiter which can be used instead of commas. Instead of:

```
DialogInput (Actor (), D, "one", "two", "three")
```

We instead use:

```
DialogInput (Actor (), D, "one,two,three")
```

Or:

```
DialogInput (Actor (), D, "one, please|two, please|three, please", "|")
```

Among the other changes are: new default color values for the `DialogOutput` command. Now unspecified text color will result in white text, rather than black. Default color values for most commands which accept a RGB color value have been set as white (255,255,255) so that forgetting to set the value will not result in a crashed script.

The `GiveItem` command now defaults to 1 if no number of items is set. This allows the command to be used as `GiveItem(Actor(), "Razor Mace")` to give a single item. If you think a command should have a default value, try it, it just may be in there.

Also, in the list of enhancements, due to the confusion regarding the `ActorGroup()` and `SetActorGroup()` commands, it was decided to create a mirror commands `ActorGuild()` and `SetActorGuild()` which have the same usage as the `ActorGroup()` commands.

Now for some of the new commands which are currently only present in the BVM version of the scripting language. `BanPlayer()`, `KickPlayer()` and `RefreshScripts()` have been added to the Scripting language and should be self explanatory. `BanPlayer()` will ban the account of the supplied `Actor()`, `KickPlayer()` will boot the `Actor()` from the server and `RefreshScripts()` will allow for reloading all scripts from disk into memory. Currently running scripts will not be affected, but all newly created script instances will be from the scripts which were last reloaded.

There is now a new *optional* script which will run at server shutdown, named **Shutdown.rsl**. This script can be used to perform various backup procedures prior to a server shutdown. Unlike all other scripts, the Shutdown script will not release any time back to the server and will run exclusively until its completion.

Project conversion

Converting a project for use with RC_BVM is generally not a difficult process. This primarily involves exchanging the old operators for the new ones, replacing the RC Standard comment characters (//) for the new RC_BVM comment character (;), reworking the DialogInput commands and rewriting the old GoTo and GoToIf loop structures to use the new standard control structures.

To aid in the conversion process, RC_BVM comes with a utility which will do the bulk of the work for you, on every script in a specified folder. This utility will replace all of the changed assignment and comparison operators, replace all logic operators, replace all comment characters, make changes to the DialogInput command and create a log file detailing the changes made for each script file.

The utility will NOT rewrite the GoTo and GoToIf commands, but will instead comment them out and make a note in the log file that the loops need to be rewritten.

Let's have a look at converting a small script for use with RC_BVM. We'll be using the default **Death.rcscript** file which ships with RC Standard. Here is the script before conversion:

```
// Default death script for player characters
// You may alter this script however you like, but DO NOT RENAME OR DELETE IT
// The entry function for this script is always "Main"
// The context actor for the script is set to whoever killed the player
Function Main()

    // Death animation
    Output(Actor(), "You have died...")
    Death = Rand(1, 3)
    If (Death == 1)
        AnimateActor(Actor(), "Death 1", 0.2, 0)
    ElseIf (Death == 2)
        AnimateActor(Actor(), "Death 2", 0.2, 0)
    Else
        AnimateActor(Actor(), "Death 3", 0.2, 0)
    EndIf

    // Wait
    DoEvents(1000)

    // Restore some health and take away some gold
    SetAttribute(Actor(), "Health", 50)
    ChangeGold(Actor(), -10)

    // Warp back to area start
    Warp(Actor(), ActorZone(Actor()), "Start")

    // Done
    Return()

End Function
```

After running the rscript2rsl utility, we have a file named **Death.rsl** containing this:

```
; Default death script for player characters
; You may alter this script however you like, but DO NOT RENAME OR DELETE IT
; The entry function for this script is always "Main"
; The context actor for the script is set to whoever killed the player
Function Main()

    ; Death animation
    Output(Actor(), "You have died...")
    Death = Rand(1, 3)
    If (Death = 1)
        AnimateActor(Actor(), "Death 1", 0.2, 0)
    ElseIf (Death = 2)
        AnimateActor(Actor(), "Death 2", 0.2, 0)
    Else
        AnimateActor(Actor(), "Death 3", 0.2, 0)
    EndIf

    ; Wait
    DoEvents(1000)

    ; Restore some health and take away some gold
    SetAttribute(Actor(), "Health", 50)
    ChangeGold(Actor(), -10)

    ; Warp back to area start
    Warp(Actor(), ActorZone(Actor()), "Start")

    ; Done
    Return

End Function
```

Notice that very little has changed in this script. In the script folder can also be found the Conversion Log.txt file containing the details of the conversion process of every *.rscript file in the scripts folder. An example of the log is below:

--Death.rsl

Line 10: '==' replaced with the '=' operator. See Notes.

Line 12: '==' replaced with the '=' operator. See Notes.

Line 29: 'Return()' has changed. See Notes.

=====

Notes:

1. The operators \$+, \$=, ==, & and | are no longer supported.
'\$+' And '\$=' now use the '+' And '=' operators.
'==' has been replaced by '='. & now uses the keyword AND.
'|' now uses the keyword Or.
2. GoTo(), GoTolf() and .Labels are no longer supported. All control structures using these keywords must be rewritten using For/Next, While/Wend or Repeat/Until.
3. DialogInput() now uses a single comma delimited string of options.

An optional delimiter can be used if necessary.

Example: `DialogInput(Actor(), D, "Option1,Option2,Option3")`

Or `DialogInput(Actor(), D, "Option1|Option2|Option3", "|")`

4. `Return()` causes problems due to the `()`. Simply use `'Return'`
Or do Not use `Return` when nothing is returned.

5. The `!'` (NOT) symbol is no longer supported, use `'<>'` instead of `!'` or `!='`.

In this instance, the conversion is complete. There is no need to perform any further editing for this script to work with `RC_BVM`. In some instances it will be necessary to rewrite any loops present. Now would also be a good time to go through and explicitly declare any variables to avoid possible errors due to expecting the wrong data type.

Include and Using

The *include* keyword is used to include code from another file. The included file is essentially inserted into the calling file as if it were written into that file. This allows spreading the code for your script among several different files. This is one method of keeping your code organized into manageable chunks, or keeping often used functions in a single file. The format is **Include** “myIncludeFile.rsl” and should be found at the beginning of your script before any function declarations.

Below, is a sample file with a couple of functions which do some simple text manipulation. If we were to find that we were using these functions rather often, we could easily include these functions in our scripts.

TextStuff.rsl:

```
Function RevText$(S$)

    ; This function reverses the order of the characters of a supplied string
    Length = Len(S)

    For i = 0 To Length
        Result$ = Result + Mid$(S, Length - i, 1)
    Next

    Return Result

End Function

Function FirstCap$(S$)

    ; This function capitalizes the first character in a supplied string
    ; A holds the upper case version of the first character on the left side
    ; of the string
    A$ = Upper$(Left$(S, 1))

    ; B holds the rest of the string
    B$ = Right$(S, Len(S) - 1)

    ; Result now holds the reunited string
    Result$ = A + B

    Return Result

End Function
```

Including and using this file is a very simple process:

myScript.rsl:

```
Include "TextStuff.rsl"

Function Main()

    Player = Actor()
    namePlayer$ = Name(Player)
    nameReverse$ = RevText(namePlayer)

    ; Change the players name to it's reverse spelling
    SetName(Player, nameReverse)

End Function
```

Module Creation

Taking the *include* concept to the next level, we have the *Using* keyword. Like the *Include* keyword, *Using* allows us to access functions from another file, except *Using* links to functions from a pre-compiled module. Unlike *Include*, *Using* does not copy any data into our script, instead it makes the functions from the module available to our script. These precompiled modules can be thought of as a library of functions that any script can access at any time by simply using the *Using* keyword. The format is *Using* “myModule.rcm” and, like *Include*, should be located at the beginning of your script.

As an exercise, lets go through the process of creating a module. In our example, we wish to precompile the file which we included earlier. Notice that there is only one difference between this file and the file we included earlier.

[module source]

```
!Compile

Function RevText$(S$)

    ; This function reverses the order of the characters of a supplied string
    Length = Len(S)

    For i = 0 To Length
        Result$ = Result + Mid$(S, Length - i, 1)
    Next

    Return Result

End Function

Function FirstCap$(S$)

    ; This function capitalizes the first character in a supplied string
    ; A holds the upper case version of the first character on the left side
    ; of the string
    A$ = Upper$(Left$(S, 1))

    ; B holds the rest of the string
    B$ = Right$(S, Len(S) - 1)

    ; Result now holds the reunited string
    Result$ = A + B

    Return Result

End Function
```

When the first line of a script is **!Compile** this tells the server to compile this **.rsl** file into a byte code module named *sourcefile.rcm* and place it into the scripts folder. Using this module is much the same as using the include file:

myScript.rsl:

```
Using "TextStuff.rcm"

Function Main()

    Player = Actor()
    namePlayer$ = Name(Player)
    nameReverse$ = RevText(namePlayer)

    ; Change the players name to it's reverse spelling
    SetName(Player, nameReverse)

End Function
```

Just as with the Include file our functions become available to the script. Unlike the Include file the code is not actually copied into the script. One of the benefits of using modules is that it then becomes possible to share your code without having to share the source. Your functions can be compiled into a module and distributed to other users of RC_BVM for use in their projects, and your source code is never exposed.

Another runtime flag which can be used with RC_BVM is the **!altsyntax** flag. Simply place the keyword *!altsyntax* at the beginning of your script and this tells the server to use an alternate syntax when processing the script. The alternate syntax makes the scripting language a little more like other Object Oriented languages in style. The differences are in the comment designation character (' rather than ;) and in the method which the scripting language accesses types.

A more detailed explanation of the core scripting language can be found in the Brisk VM scripting language manual, and this manual almost exclusively covers the alternate syntax. The BVM_SL manual can be found by opening the RC_BVM script editor.

This covers the major changes incorporated in RC_BVM. Now that we are at the end of this guide, I would like to encourage everyone with an interest in Virtual Machines and scripting languages to download the BVM2 trial, and see how easy it is to incorporate and how powerful it can be.

<http://www.koriolis-fx.com/>